Ground Motions and Source Properties of Natural Vs Induced Earthquakes

Chris H. Cramer
CERI, University of Memphis
A Presentation at the Induced
Seismicity Workshop in Oklahoma
City, OK
November 18, 2014



Outline

Decay with Distance and Crustal Attenuation


Brune Stress Parameter Estimates

 Earthquake dependent systematic variations (event terms)



Crustal Attenuation

- Earthquake wave attenuation is proportional to the inverse of Seismic Quality factor (Q).
- Q is frequency dependent
 - $-Q(f) = Qo f^{\eta}$
- Gulf Coast Q is different from Mid-Continent Q
 - Gulf Coast Qo (1 Hz Q) is 250 to 300
 - Mid Continent Qo is 500 to 600



Regional Q Trends


- Earthquakes in Oklahoma and Arkansas are near the Q transition from Mid-Continent to Gulf Coast Q
 - Earthquake wave paths to the North show Mid-Continent Q values
 - Earthquake wave paths to the South show Gulf
 Coast Q values
- Earthquake wave paths in Texas show Gulf Coast Q values




Brune Stress Parameter

- Brune stress parameter is a measure of the highfrequency energy content relative to the lowfrequency energy level.
- For a given earthquake magnitude, a higher stress parameter implies larger high-frequency amplitudes and hence potentially greater damage.
- There is a suggestion that shallow earthquakes (< 5 km hypocenters) tend to have lower stress parameters than deeper earthquakes.








Potentially Induced Earthquake (PIE) Brune Stress Parameters

- Published average for ENA earthquakes is 14 MPa
- Limited Number of Initial Estimates:
 - M4.4 2010-10-15 Guy AR -> 8 MPa
 - M4.2 2010-11-20 Guy AR -> 8 MPa
 - M4.7 2011-02-28 Greenbrier AR -> 8 MPa
 - M4.3 2010-10-13 Slaughterville OK -> 10 MPa
 - M5.6 2011-11-06 Prague OK -> 10 MPa
 - M4.6 2011-10-30 Comal TX -> ~5 MPa
 - M4.3 2012-05-17 Timpson Tx -> ~5 MPa ?
 - M3.7 2011-12-31 Youngstown OH -> ~ 5 MPa
- M4.8 2014-11-12 Conway Springs KS -> ~5 MPa






Event Term Analysis

 Event Terms show systematic variations among earthquakes

- Preliminary results by Justin Hollenback for NGA East project at PEER Center
 - All earthquakes outside Gulf Coast
 - Shallow earthquakes outside Gulf Coast




Updated Model: Event-Terms





Updated Model: Shallow Event-Terms





Summary

- Observed ground motions from Arkansas, Oklahoma, and Texas earthquakes can be affected by higher regional attenuation in the Gulf Coast.
- Potentially Induced Earthquakes tend to have below average Brune Stress parameters in the range of 5 to 10 MPa.
- Potentially Induced Earthquakes tend to be shallow with event terms similar to shallow tectonic earthquakes and have about 20–30% lower short-period ground motions than average.

